

User manual

The RHFAD128 GUI

Introduction

The RHFAD128 is specifically designed to sustain ionizing dose and heavy ions for space applications by using a high-end proven CMOS technology.

This device is a low-power, multiplexed eight-channel 12-bit analog-to-digital converter for conversion from 50 ksps to 1 Msps. The architecture is based on the successive-approximation register with internal track-and-hold. The RHFAD128 features 8 analog inputs that can be programmed to be either 8 single-ended or 4 differential inputs using the control register bits. The output serial data are straight binary and are compatible with SPI.

EVAL-RHFAD128V2 is the evaluation board of the RHFAD128.

This board can be connected to a NUCLEO-L476RG and be monitored with a graphical user interface (GUI): the RHFAD128_GUI.



1 Getting started

1.1 System requirements

The RHFAD128_GUI software needs the following system requirements to perform:

Table 1. System requirements

Main c	omponents
NUCLEO-L476RG	STM32 Nucleo development board
Mini-B USB cable	With USB data support
AKI_BIN_for_NucleoL476RG	Software for Nucleo
RHFAD128_GUI	RHFAD graphical user interface
EVAL-RHFAD128V2	RHFAD128 evaluation board
Operating system	Windows OS
STSW-LINK009	SW for Nucleo connection

1.2 Hardware configuration

1.2.1 RHFAD128 (EVAL-RHFAD128V2)





Figure 1. EVAL-RHFAD128V2

UM3165 - Rev 1 page 2/14



Connect the EVAL-RHFAD128V2 to the Nucleo using the following pinout.

Figure 2. SPI connectors on the EVAL-RHFAD128V2 and the pinout for the connection to the Nucleo



Nucleo PIN	SPI pin
PB12	Chip select
PB13	SCLK
PB14	MISO
PB15	MOSI

1.3 Software configuration

1.3.1 Nucleo connection

1 - Connect the NUCLEO-L746RG to the laptop using a Mini-B USB cable:






2 - Please make sure that STLINK is installed and up to date:

UM3165 - Rev 1 page 3/14



Figure 4. STLINK must be installed



- 3 Launch the RHFAD128 GUI
- a. Unzip the zipped folder RHFAD128_GUI.zip

Figure 5. There are two documents: RHFAD128_GUI folder containing the RHFAD128_GUI.exe to launch on the laptop - AKI_Bin_for_NucleoL476RG.bin to upload in the Nucleo



4 - Upload the binary into the STM32 Nucleo board

Connect the Nucleo board to the PC using a USB Mini-B cable, drag and drop the binary file to the Nucleo board (NODE_L476RG)

use the binary file: AKI Bin for NUCLEOL476RG.bin

Figure 6. This file must be uploaded in the Nucleo



UM3165 - Rev 1 page 4/14



2 Use of the GUI

In the RHFAD128_GUI folder, click on the RHFAD128_GUI.exe file to open the GUI. The following window must appear.

RHFAD128 GUI X Settings RHFAD128 Voltage reference(V): 3.3 Channel: channel 0 Output data type : Hexadecimal Single read mode Single Read Single read result Waveform chart 0.04 0.02 0.00 -0.02 -0.04-0.04-0.02 0.00 0.02 0.04 time Start plot Stop plot Clear plot

Figure 7. Device selection window

UM3165 - Rev 1 page 5/14



Figure 8. RHFAD128_GUI interface




Table 2. SPI speed used by the GUI to communicate with the RHFAD128

Product	SPI speed used by the GUI
RHFAD128	500 Msps


UM3165 - Rev 1 page 6/14



3 Troubleshooting

3.1 Device not found

Figure 9. Device not found window



Issue:

The Nucleo board is not detected

Resolution:

- Please connect the appropriate Nucleo board
- Be sure that STLINK is installed and up to date
- · It is also better to have only one Nucleo board connected to the computer
- Then click on "OK".

UM3165 - Rev 1 page 7/14



3.2 Connection issue

Figure 10. Connection issue message



Issue:

• In case of unwanted disconnection or a problem in reading the device, the message <u>"Connection issue"</u> appears in the Single read mode communication box.

Resolution:

- Close the GUI and disconnect/reconnect the Nucleo board and restart the GUI
- If the problem persists, check if the board is correctly connected.

UM3165 - Rev 1 page 8/14





4 List of acronyms

Table 3. List of acronyms

Term	Meaning
GUI	Graphical user interface

UM3165 - Rev 1 page 9/14



Revision history

Table 4. Document revision history

Date	Version	Changes
29-May-2023	1	Initial release.

UM3165 - Rev 1 page 10/14



Contents

1	Gett	ing started	2
	1.1	System requirements	
	1.2	Hardware configuration	
		1.2.1 RHFAD128 (EVAL-RHFAD128V2)	2
	1.3	Software configuration	3
		1.3.1 Nucleo connection	
2	Use	of the GUI	5
3	Trou	ıbleshooting	7
	3.1		
	3.2	Connection issue	8
4	List	of acronyms	
Rev		history	



List of tables

Table 1.	System requirements	2
Table 2.	SPI speed used by the GUI to communicate with the RHFAD128	6
Table 3.	List of acronyms	S
Table 4.	Document revision history	C

UM3165 - Rev 1 page 12/14





List of figures

Figure 1.	EVAL-RHFAD128V2	2
Figure 2.	SPI connectors on the EVAL-RHFAD128V2 and the pinout for the connection to the Nucleo	3
Figure 3.	NUCLEO-L476RG used to run the GUI	3
Figure 4.	STLINK must be installed	4
Figure 5.	There are two documents: RHFAD128_GUI folder containing the RHFAD128_GUI.exe to launch on the laptop - AKI_Bin_for_NucleoL476RG.bin to upload in the Nucleo	
Figure 6.	This file must be uploaded in the Nucleo	4
Figure 7.	Device selection window	5
Figure 8.	RHFAD128_GUI interface	6
Figure 9.	Device not found window	7
Figure 10.	Connection issue message	8

UM3165 - Rev 1 page 13/14



IMPORTANT NOTICE - READ CAREFULLY

STMicroelectronics NV and its subsidiaries ("ST") reserve the right to make changes, corrections, enhancements, modifications, and improvements to ST products and/or to this document at any time without notice. Purchasers should obtain the latest relevant information on ST products before placing orders. ST products are sold pursuant to ST's terms and conditions of sale in place at the time of order acknowledgment.

Purchasers are solely responsible for the choice, selection, and use of ST products and ST assumes no liability for application assistance or the design of purchasers' products.

No license, express or implied, to any intellectual property right is granted by ST herein.

Resale of ST products with provisions different from the information set forth herein shall void any warranty granted by ST for such product.

ST and the ST logo are trademarks of ST. For additional information about ST trademarks, refer to www.st.com/trademarks. All other product or service names are the property of their respective owners.

Information in this document supersedes and replaces information previously supplied in any prior versions of this document.

© 2023 STMicroelectronics – All rights reserved

UM3165 - Rev 1 page 14/14